

# Configuration notifications PWA

## Configuration système

### Génération de la clé

```
openssl ecparam -name prime256v1 -genkey -noout -out vapid_private.pem
openssl ec -in vapid_private.pem -pubout -out vapid_public.pem
openssl ec -in vapid_private.pem -outform DER|tail -c +8|head -c 32|base64|tr -d '=' |tr '/+' '_-'
> vapid_private_key.txt
openssl ec -in vapid_private.pem -pubout -outform DER|tail -c 65|base64|tr -d '=' |tr '/+' '_-' >
vapid_public_key.txt
```

### Pointer les clés dans la configuration

Dans `var/lib/combo/tenant/nom-du-tenant/settings.json`, ajouter :

```
"PWA_VAPID_PUBLIK_KEY": "contenu de vapid_public_key.txt",
"PWA_VAPID_PRIVATE_KEY": "contenu de vapid_private_key.txt",
"PWA_VAPID_CLAIMS": {
  "sub": "mailto:admin+whatever@yourdomain.com"
}
```